



Notes on the preparation of VDA 4921

VDA 4921 refers to VDA 4913 via the consignment/cargo reference number and the reference to the delivery bills.

The following fields from the EDI consignment note/shipping order are important for the creation of VDA4921:

Nr.	VDA 4921	Speditionsauftrag	DFÜ Warenbegleitschein	Bemerkung	Quelle VDA 4913
1	Satzart 751, Pos. 03	Empfangswerk	Empfänger-Werk-Kunde	Mercedes-Benz Empfangswerk	Satzart 711, Pos. 03*
2	Satzart 754, Pos. 03	Lieferanten-Nr.	Lieferant-NR	Lieferantenummer (8/9 stellig) angeben	Satzart 713, Pos. 16
3	Satzart 754, Pos. 04	Sendungs- /Ladungs- Bezugs Nummer	Sendungs-NR	Bezugsnummer, die der Lieferant der Sendung zuordnet	Satzart 712, Pos. 03
4	Satzart 754, Pos. 08	Brutto-Gewicht kg	Send. – Gewicht BR	Warengewicht einschließlich Verpackung	Satzart 712, Pos. 08
5	Satzart 755, Pos. 04	Lieferschein- Nummer	LS-NR	8-stellige Lieferschein- Nummer	Satzart 713, Pos. 03

This data can also be transferred to your transport management system via remote data transmission

Pros:

- No manual entry of supplier data
 - No typing errors
 - No reference errors (Supplier number incl. index, consignment and delivery bill number)
- Corrected or updated data
- Package numbers from VDA 4913 can be used for scanning
 - Requirements
 - Supplier sends EDI

You can find all relevant information here:

[Trefferliste \(daimler.com\)](#)

EDI – Manual chapter 12



- Recommendations from the RDT manual chapter 12:
- 1.4: Relevant fields from the goods accompanying documents
- 1.3: Entry and verification of data via the IBL platform

IBL Support
E-Mail: ibl-support@mercedes-benz.com
Tel: +49 (0)30 / 887 215 588

19.04.2022